

nanoVNA-H4 software support under Ubuntu

Introduction

This is a work in progress.

External control

NanoVNA Saver

NanoVNA Saver¹ is an auxiliary program which supports:

- saving Touchstone files
- segmented sweeps, to permit increasing the number of frequency points
- an arbitrary number of associated calibration sets
- displaying and analysing resulting data

Installing NanoVNA Saver under Ubuntu 18.04

This procedure will be different under Ubuntu 20.04.

This procedure is adapted from that suggested by the repository². *In essence, success is due to the use of a Python Virtual Environment to isolate NanoVNA Saver & its associated Python requirements from anything else on the host machine.*

Install Python 3.7

This is required to run NanoVNA Saver, but must be installed in such a way as to retain Python 3.6 as the default Python 3 version.

- Install Python 3.7 and pip

```
sudo apt install python3.7 python3-pip
```

- Install Python 3.7 development files

```
sudo apt install python3.7-dev
```

It is now necessary to ensure that the default version of Python 3 remains 3.6, using the **update-alternatives** mechanism³.

¹ See <https://github.com/mihtjel/nanovna-saver>.

² Noted at <https://github.com/mihtjel/nanovna-saver#ubuntu-1804--1904>.

³ This process is inspired by, and adapted from, <https://unix.stackexchange.com/questions/410579/change-the-python3-default-version-in-ubuntu>, top answer.

```
sudo update-alternatives --install /usr/bin/python3 python3  
/usr/bin/python3.7 1
```

```
sudo update-alternatives --install /usr/bin/python3 python3  
/usr/bin/python3.6 2
```

```
sudo update-alternatives --set python3 /usr/bin/python3.6
```

Install NanoVNA Saver itself

This process is distilled from a document⁴ referenced on the support group Wiki⁵. NanoVNA Saver is installed into, and run from, a **Python Virtual Environment (PVE)**⁶.

- Install the **Python 3.7 virtual environment**:

```
sudo apt install python3.7-venv
```

- Install Git

```
sudo apt install git
```

- Make a **directory** to hold Python virtual environments:

```
cd
```

```
mkdir ~/.venv
```

- Create a **new PVE** for NanoVNA Saver, but **without pip**:

```
cd ~/.venv
```

```
python3.7 -m venv nvna-s --without-pip
```

- Activate the newly created **PVE**:

```
source ~/.venv/nvna-s/bin/activate
```

The **PVE** is now, effectively, an isolated instance of Python in to which NanoVNA Saver may be installed, fuss-free.

- Note that the command prompt is now prefixed by the **PVE's** name:

```
(nvna-s) user@host:~/.venv$
```

- Install the latest version⁷ of **pip** and associated support (**setuptools** & **wheel**)

```
curl https://bootstrap.pypa.io/get-pip.py | python
```

⁴ Document found at [https://groups.io/g/nanovna-users/files/NanoVNA PC Software/NanoVNA-Saver/nvna-s-pve-rev-c.pdf](https://groups.io/g/nanovna-users/files/NanoVNA%20PC%20Software/NanoVNA-Saver/nvna-s-pve-rev-c.pdf).

⁵ Wiki entry at <https://groups.io/g/nanovna-users/wiki/12336#Python>.

⁶ Outlined at <https://docs.python.org/3.7/tutorial/venv.html>.

⁷ The version of **pip** associated with Python 3.7 is not the most up-to-date.

- At the end of this process there should be two lines similar to:

```
Installing collected packages: pip, setuptools, wheel
```

```
Successfully installed pip-20.1.1 setuptools-46.4.0 wheel-0.34.2
```

- Clone the source code from GitHub in to the PVE:

```
git clone https://github.com/mihtjel/nanovna-saver
```

- Install the dependencies and build NanoVNA Saver⁸:

```
cd ~/.venv/nvna-s/nanovna-saver
```

```
python3.7 -m pip install .
```

- Now run NanoVNA Saver (**nanovna-saver.py**) and test

```
python3.7 ./nanovna-saver.py
```

- Check that the program runs, and behaves roughly as expected.
- Quit the PVE, and return to the home directory

```
deactivate
```

```
cd
```

Make a script

In your favourite editor, make a script⁹ **~/bin/nanovnaSaver.sh**:

```
#!/bin/bash
```

```
# nanovnaSaver.sh
```

```
# This script runs NanoVNA Saver from a PVE
```

```
# Adapted from a similar script by Nick, G3VNC
```

```
# RAG, 2020-05-22
```

```
cd
```

```
# Enter the PVE
```

```
source ~/.venv/nvna-s/bin/activate
```

```
# Run our program
```

```
python3.7 ~/.venv/nvna-s/nanovna-saver/nanovna-saver.py
```

```
# Program finished, leave the PVE cleanly
```

⁸ The dependencies are brought in automatically.

⁹ This procedure assumes that **~/bin** already exists, and that **~/bin** is included in the **PATH** environmental variable.

deactivate

Make the script executable:

```
chmod +x ~/bin/nanovnaSaver.sh
```

Finally, add a **menu entry**. There is an icon file in the source¹⁰.

Installing NanoVNASaver under Ubuntu 20.04

For Ubuntu 20.04, the default Python version is 3.8. Using the PVE still seems like a very smart move, though¹¹.

Firmware

Setting firmware update mode

Setting the nanoVNA-H4 in to DFU mode requires the following procedure¹²:

- Power off NanoVNA-H4
- Press down the jog switch
- Power on
- Release jog switch

At this point, the nanoVNA-H4 is in DFU mode, with a **blank screen**¹³.

For further investigation!

Octave interfacing

There is an example script available¹⁴, which demonstrates how a **nanoVNA** may be controlled from **Octave**. Although the example is written with Windows in mind, it may readily be adapted to **Linux**. There is a syntax mistake which must be corrected¹⁵, and then the example script permits measuring VSWR over a self-defined set of radio bands. The key component is the **Instrument Control** package at **Octave Forge**¹⁶.

The virtue of the example is to demonstrate controlling the **nanoVNA** from **Octave**, in principle for any application.

Not yet tested!

¹⁰Icon file at https://github.com/mihtjel/nanovna-saver/blob/master/icon_48x48.png.

¹¹Not yet investigated in practice.

¹²Noted at <https://groups.io/g/nanovna-users/message/10140>.

¹³As noted at <https://groups.io/g/nanovna-users/message/10149>.

¹⁴From GitHub, at <https://github.com/PromptusCTO/K1YBE>.

¹⁵Correction noted at <https://groups.io/g/nanovna-users/message/13860>.

¹⁶More informaation at <https://octave.sourceforge.io/instrument-control/>.

Appendix A: GitHub nanoVNA Saver install process

The following process is **likely to fail** due to version dependency issues, relating to PyQt5.

This process is elaborated from the GitHub description¹⁷. **Python 3.7**, or later, must already be installed¹⁸.

- Firstly install a specific version of PyQt5¹⁹:

```
sudo python3.7 -m pip install pyqt5==5.14
```

- Make a suitable directory to hold the code directory²⁰, and **cd** to it
- Clone the repository

```
git clone https://github.com/mihtjel/nanovna-saver
```

- **cd** to the source directory

```
cd nanovna-saver
```

- perform a **pip** installation

```
python3.7 -m pip install .
```

Test the installation:

```
python3.7 nanovna-saver.py
```

RAG 2020-06-03

¹⁷Install process given at <https://github.com/mihtjel/nanovna-saver#installation-and-use-with-pip-1>.

¹⁸This process is understood to be effective with Fedora and other distributions. Debian and derivatives display issues.

¹⁹As noted at https://www.reddit.com/r/learnpython/comments/fjm1cp/stuck_trying_to_run_nanovnasaver_via_pyqt5_on/. [Note the description of the full code is not quite right.]

²⁰Such as **~/code**, but may be any directory to which the user has write access.